



HOT Wallet setup Windows

Prerequisite

- Windows Machine

- 1.) Record down your server IP address by running the ipconfig on Command Prompt in this scenario IP Address: 195.231.9.123

```
Administrator: Command Prompt
Microsoft Windows [Version 10.0.14393]
(c) 2016 Microsoft Corporation. All rights reserved.

C:\Users\Administrator>ipconfig

Windows IP Configuration

Ethernet adapter Lan 3:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . :

Ethernet adapter Lan 2:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . :

Ethernet adapter Lan 1:

    Connection-specific DNS Suffix  . :
    Link-local IPv6 Address . . . . . : fe80::436:4be6:a0c8:ef1b%7
    IPv4 Address. . . . . : 195.231.9.123
    Subnet Mask . . . . . : 255.255.255.0
    Default Gateway . . . . . : 195.231.9.1

Tunnel adapter isatap.{E336B7C4-A259-4A11-BDAF-FC6669152A3A}:

    Media State . . . . . : Media disconnected
    Connection-specific DNS Suffix  . :
```

- 2.) Load up your beetlecoin wallet and send the collateral 10k for Basic Node, 50k for Classic Node and 150k for Standard node and wait for 20 confirmations

BeetleCoin Core - Portafoglio

File Impostazioni Strumenti Aiuto

RECEIVE

Use this form to request payments. All fields are optional.

Label: BasicNode2

Address: XPURPgY8tyHD7KqZ8Kuvht72J5GeBGZaxF

Amount: [dropdown] BEET

Message:

Reuse an existing receiving address (not recommended)


[Request payment](#) [Clear](#) [Receiving Addresses](#)

Requested payments history

Data	Etichetta	Address	Message	Ammontare (BEET)
02/06/2019 11:02	BasicNode1	XNHJvkfX2DFZ...	(no message)	(no amount)


[Show](#) [Remove](#)

- 3.) In Debug console window enter "masternode genkey" and copy the result. This is your MASTERNODEPRIVKEY. For this scenario private key is 5H389SgoZPnhC5PoHDCHGDFUEbjXrmJmMeNmqqhgwFRk3hvpU7U



- 4.) In Debug console window enter "masternode outputs" and copy the result. "txhash" is your YOURTXID. "outputidx" is YOUROUTPUTIDX

"txhash": "3040e2ff5b90fed79cd0b1ca9b0870c5d66f9b871c63136b466b4822876bb83c",
"outputidx": 1



- 5.) Open your wallet configuration file in Notepad. This config file is located at C:/users/Administrator/appdata/roaming/beetlecoin (or your own custom path for beetle coin installation) then paste the configuration below. Ensure that the IP address matches your IP then save the file.

```
externalip=195.231.9.123
#bind=195.231.9.123:3133
port=3133
rpcallowip=127.0.0.1
rpcport=3134
rpcbind=127.0.0.1
daemon=1
server=1
listen=1
masternode=1
masternodeaddr=195.231.9.123:3133
masternodeprivkey=5H389SgoZPnhC5PoHDCHGDFUEbjXrmJmMeNmqqhgwRk3hvpU7U
shrinkdebuglog=1
logtimestamps=1
logips=1
```

- 6.) Open Masternode.conf. This config file is located at C:/users/Administrator/appdata/roaming/Beetlecoin/masternode.conf

Then paste in the following.

```
MN1 YOURIP:3133 MASTERNODEPRIVKEY YOURTXID YOUROUTPUTIDX
```

Example for this scenario as below

```
MN1 195.231.9.123:3133 5H389SgoZPnhC5PoHDCHGDFUEbjXrmJmMeNmqqhgwRk3hvpU7U
3040e2ff5b90fed79cd0b1ca9b0870c5d66f9b871c63136b466b4822876bb83c 1
```

Save the file and restart your beetlewallet.

- 7.) Go to Masternodes Tab and start your Masternode by clicking on 'Start all' or 'Start alias'. You will see the response "Masternode started successfully".

BeetleCoin Core - Wallet

File Settings Tools Help

My Masternodes All Masternodes

Note: Status of your masternodes in local wallet can potentially be slightly incorrect. Always wait for wallet to sync additional data and then double check from another node if your node should be running but you still see "MISSING" in "Status" field.

Alias	Address	Type	Protocol	Status	Active	Last Seen (UTC)	Pubkey
MN1	195.231.9.123:3133	Basic No...	70104	ENABLED	00m:00s	2019-06-02 09:40	XNHJvkfX2DFZncWK...

Start alias Start all Start MISSING Update status Status will be updated automatically in (sec): 47

8.) Use the debug console to see the status of your Masternode by typing master node status

Tools window

Information Console Network Traffic Peers Wallet Repair

```

11:44:35 Welcome to the BeetleCoin RPC console.
Use up and down arrows to navigate history, and Ctrl-L to clear screen.
Type help for an overview of available commands.

WARNING: Scammers have been active, telling users to type commands here, stealing
their wallet contents. Do not use this console without fully understanding the
ramifications of a command.

11:45:44 masternode status
11:45:44 {
  "txhash": "3040e2ff5b90fed79cd0b1ca9b0870c5d66f9b871c63136b466b4822876bb83c",
  "outputidx": 1,
  "netaddr": "195.231.9.123:3133",
  "addr": "XNHJvkfX2DFZncWKNHjLQutoyatEDscZcq",
  "status": 4,
  "message": "Masternode successfully started"
}

```

9.) After few minutes you will be able to see the active time of your node

BeetleCoin Core - Wallet

File Settings Tools Help

My Masternodes All Masternodes

Note: Status of your masternodes in local wallet can potentially be slightly incorrect. Always wait for wallet to sync additional data and then double check from another node if your node should be running but you still see "MISSING" in "Status" field.

Alias	Address	Type	Protocol	Status	Active	Last Seen (UTC)	Pubkey
MN1	195.231.9.123:3133	Basic No...	70104	ENABLED	07m:00s	2019-06-02 09:47	XNHJvkfX2DFZncWK...

Start alias Start all Start MISSING Update status Status will be updated automatically in (sec): 42